

NEW ORIGIN FOR SPIN CURRENT AND CURRENT-INDUCED SPIN PRECESSION IN MAGNETIC MULTILAYERS

L. BERGER

Physics Department, Carnegie Mellon University, Pittsburgh, PA
15213

In metallic ferromagnets, an electric current is accompanied by a flux of angular momentum, also called spin current. In multilayers, spatial variations of the spin current correspond to drive torques exerted on a magnetic layer. These torques result in spin precession above a certain current threshold. The usual kind of spin current is associated with translation of the spin-up and spin-down Fermi surfaces in momentum space. We discuss a different kind of spin current, associated with expansion and contraction of the Fermi surfaces. It is more nonlocal in nature, and may exist even in locations where the electrical current density is zero. It is larger than the usual spin current, in a ratio of 10 or 100, at least in the case of one-dimensional current flow. The new spin current is proportional to the difference $\Delta\bar{\mu} \simeq 10^{-3}eV$ between spin-up and spin-down Fermi levels, averaged over the entire Fermi surface. Conduction processes, spin relaxation, and spin-wave emission in the multilayer can be described by an equivalent electrical circuit resembling an unbalanced dc Wheatstone bridge. And $\Delta\bar{\mu}$ corresponds to the output voltage of the bridge.

I. INTRODUCTION

In magnetic multilayers, the s-d exchange interaction causes ¹ an increase of the Gilbert spin-damping parameter α near an interface. In the presence of a dc current normal to layers, it also generates ¹⁻⁵ drive torques on magnetic spins near the interface; these lead to a spin precession above a certain current threshold. This current-induced precession has been observed recently ⁶⁻⁸ in Co/Cu multilayers. Such device, which we call a SWASER, is the magnetic analog of the semiconductor laser diode. Current-induced switching between opposite static magnetic-spin directions has also been observed ^{7,8}, at low magnetic fields; it happens probably through a temporary current-induced precession. Microwave-frequency ac currents have also been used ⁹ to excite precession in a multilayer. Detailed numerical as well as analytical calculations of dc current-induced precession and switching have been done ¹⁰ for various thin-film geometries and anisotropy-field cases. A physically different mechanism has been proposed ¹¹

for current-induced switching.

The layer configuration most common in theory and experiments is shown in Fig. 1a. Magnetic layer F_1 prepares the spin of conduction electrons in a fixed specific direction. It must be ¹ thicker than a spin-diffusion length, in order to ensure a ratio α_1 of spin-up to spin-down current as different from one as possible. The non-magnetic spacer N must be thinner than a local spin-diffusion length, to preserve spin memory for electrons crossing it. The precessing magnetic layer F_2 must be thin, as the current-induced drive torque is only applied ² to a region of F_2 of thickness $\pi/(k_\uparrow - k_\downarrow)$ near the $N - F_2$ interface. Here, $k_\uparrow$ and $k_\downarrow$ are the spin-up and spin-down Fermi wavenumbers in F_2 , both assumed real-valued. Thick non-magnetic layer N_2 acts as a current-return lead. We introduce ¹ spatial coordinates x, y, z , with x normal to layers, and $x=0$ at the $N - F_2$ interface (Fig. 1a). We also use spin coordinates x_2, y_2, z_2 , with z_2 parallel to the precessing atomic spins $\vec{S}_2$ in F_2 , and x_2 in the plane of z_2 and of the precession axis (Fig. 1b). The direction of the precession axis, which is also the direction of the total effective magnetic field, is assumed parallel to the fixed atomic spins $\vec{S}_1$ in F_1 . The $\vec{S}_1$ direction is arbitrary. The precession-cone angle between $\vec{S}_1$ and $\vec{S}_2$ is called θ .

The current-induced torque $\vec{\tau}$ on the spins of layer F_2 , responsible for maintaining the precession, can be calculated ⁴ from the angular-momentum current $\vec{P}$, also called spin current. The important components are along x_2 :

$$\tau_{x2} = P_{x2}(x=0) - P_{x2}(x=\infty). \quad (1)$$

Here, $P_{x2}(x=0)$ is calculated in F_2 at the $N - F_2$ interface, and $P_{x2}(x=\infty)$ at a point of F_2 to the right of the region $0 < x < \pi/(k_\uparrow - k_\downarrow)$ where most of the torque is applied.

The traditional spin current ⁴ arises from Fermi-surface translation, and is proportional to the local electrical-current density. The main purpose of the present paper is to describe a different kind of spin current, which comes from Fermi-surface expansion or contraction, and which can exist even where the current density is zero; this new spin current turns out to be much larger than the traditional one, at least when the current flow is one-dimensional. Another purpose is to demonstrate the equivalence of the Slonczewski and SWASER theories.

II. SPIN CURRENT FOR ONE ELECTRON

First, we consider free-electron states of wavevector $\vec{k}_N$ in N which are eigenstates of the z_2 component of spin. If $k_x^N > 0$, they enter F_2 from N , and their form in F_2 is

$$\begin{aligned} \psi_\uparrow &= \begin{vmatrix} 1 \\ 0 \end{vmatrix} f_\uparrow(\vec{r}); \quad \psi_\downarrow = \begin{vmatrix} 0 \\ 1 \end{vmatrix} f_\downarrow(\vec{r}) \\ f_\uparrow &= \frac{\exp(i\vec{k}_\uparrow \vec{r})}{V_N^{1/2}} \frac{2k_x^N}{k_x^N + k_x^\uparrow}, \quad f_\downarrow = \frac{\exp(i\vec{k}_\downarrow \vec{r})}{V_N^{1/2}} \frac{2k_x^N}{k_x^N + k_x^\downarrow}. \end{aligned} \quad (2)$$

The wavevectors $\vec{k}_\uparrow, \vec{k}_\downarrow$ are such that $\psi_\uparrow, \psi_\downarrow$ have the same energy. These states are assumed to have most of their norm in the layer N of volume V_N . Momentum conservation along y and z at the $N - F_2$ interface gives $k_y^N = k_y^\uparrow = k_y^\downarrow$ and $k_z^N = k_z^\uparrow = k_z^\downarrow$. We neglect reflections at the $F_2 - N_2$ interface.

A part of the amplitude of the actual spin-up and spin-down waves ψ_+, ψ_- entering F_2 from N with $k_x^N > 0$ originates ¹ in F_1 . Hence, the spin density $\langle \vec{s}\delta(\vec{r} - \vec{r}_0) \rangle$ for that part is parallel or antiparallel to $\vec{S}_1$, and at an angle θ to the z_2 axis. These states are linear combinations of $\psi_\uparrow, \psi_\downarrow$. With z_2 as a spin quantization axis as before, we can write in F_2 :

$$\psi_+ = T_+^{1/2} \begin{vmatrix} f_\uparrow(\vec{r})\cos(\theta/2) \\ -f_\downarrow(\vec{r})\sin(\theta/2) \end{vmatrix}; \psi_- = T_-^{1/2} \begin{vmatrix} f_\uparrow(\vec{r})\sin(\theta/2) \\ f_\downarrow(\vec{r})\cos(\theta/2) \end{vmatrix}. \quad (3)$$

We assume $\theta \ll 1$ radian, so that ψ_+, ψ_- can still be called spin-up and spin-down. The quantities $T_+ = 4k_x^\uparrow k_x^N / (k_x^N + k_x^\uparrow)^2$, $T_- = 4k_x^\downarrow k_x^N / (k_x^N + k_x^\downarrow)^2$ are the transmission coefficients at the $F_1 - N$ interface, assuming F_1 to be made of the same material as F_2 . These quantities are present because we consider only the parts of the waves in F_2 originating in F_1 . To simplify the theory, we approximate $T_+ \simeq T_- \simeq T$.

For any state ψ , Slonczewski gives ⁴ an expression for the components P_{x2}, P_{y2} of the spin current:

$$\psi = \begin{vmatrix} a(\vec{r}) \\ b(\vec{r}) \end{vmatrix}; P_{x2} + iP_{y2} = \frac{i\hbar^2}{2m} \left(\frac{da^*}{dx} b - a^* \frac{db}{dx} \right). \quad (4)$$

Using this on the $k_x^N > 0$ states ψ_+, ψ_- of Eqs.(3), we obtain in F_2 , respectively:

$$\begin{aligned} (P_{x2}(x))_+ &= -\frac{\hbar}{4} \sin\theta \frac{T(v_x^\uparrow + v_x^\downarrow)(2k_x^N)^2 \cos(k_x^\uparrow - k_x^\downarrow)x}{V_N(k_x^N + k_x^\uparrow)(k_x^N + k_x^\downarrow)} \\ (P_{x2}(x))_- &= -(P_{x2}(x))_+. \end{aligned} \quad (5)$$

Here, $v_x^\uparrow$ and $v_x^\downarrow$ are electron-velocity components in F_2 . The cosine factor comes from the precession ^{1,4} of the electron spin around the s-d exchange field set up by $\vec{S}_2$, as the electron moves toward increasing x in F_2 . We assume $k_N < k_\uparrow, k_\downarrow$ so that the $k_x^N > 0$ states are not totally reflected at the $N - F_2$ interface.

On the other hand, the $k_x^N < 0$ states originated in N_2 before traversing F_2 toward left. Because of the absence of a magnetic layer like F_1 to polarize their spin along a specific fixed direction oblique to z_2 , we have $P_{x2} = 0$ for these states, at any location in F_2 . The same applies to the part of the states in F_2 that have $k_x^N > 0$ after reflection at the $N - F_2$ interface. Also to the part (ignored earlier) that has $k_x^N > 0$ after reflection at the $F_1 - N$ interface, if $T_+ \simeq T_-$.

In thermal equilibrium, $k_x^N > 0$ spin-up and spin-down states ψ_+, ψ_- of the same energy are equally populated, and Eqs. (5) show that their P_{x2} cancel

each other in pairs. The total P_{x2} of the electron distribution vanishes, as expected from the second law since P_{x2} is related to damping and drive torques. This cancellation does not happen in general for component P_{z2} , which plays no important role anyway.

For the same reason, when out of equilibrium, only states near the Fermi level contribute to the total P_{x2} .

III. TOTAL SPIN CURRENT IN CASE OF TRANSLATED FERMİ SURFACES

The traditional calculation ⁴ of the total spin current assumes a non-zero local current density j_x , corresponding to translations of the spin-up and spin-down Fermi surfaces in N along the k_x^N axis, by amounts $\delta k_x^+, \delta k_x^-$ (Fig. 2a).

Because of the cancellation mentioned above, only states located between the spin-up and spin-down Fermi surfaces in N contribute to the total P_{x2} , at zero temperature. Also, the blurring of the electron distribution near the Fermi level, happening at non-zero temperature, turns out to have no effect on the total P_{x2} .

We integrate the P_{x2} of Eqs. (5) over all number elements d^2N of electron states, from $\alpha = 0$ to $\alpha = \pi/2$, corresponding to the $k_x^N > 0$ half of the Fermi surface in N. For given energy, $k_x^\uparrow, k_x^\downarrow$ are functions of α . As explained in the last section, only the states on that half have non-zero P_{x2} . We call ΣP_{x2} the total spin current:

$$\Sigma P_{x2}(x) = -\frac{\hbar^2 \sin\theta}{16\pi^2 m} k_N^2 (\delta k_x^+ - \delta k_x^-) \int_0^{\pi/2} T \frac{(2k_x^N)^2 (k_x^\uparrow + k_x^\downarrow) \cos((k_x^\uparrow - k_x^\downarrow)x) \cos\alpha \sin\alpha d\alpha}{(k_x^N + k_x^\uparrow)(k_x^N + k_x^\downarrow)}. \quad (6)$$

For any given $x \gg \pi/(k_\uparrow - k_\downarrow)$, the argument of $\cos((k_x^\uparrow - k_x^\downarrow)x)$ in the integral varies rapidly with α . Hence, the average of this cosine over half a Fermi surface is nearly zero. In turn, this means $\Sigma P_{x2}(x) \simeq 0$ when $x \gg \pi/(k_\uparrow - k_\downarrow)$. Thus, the last term of Eq. (1) vanishes. Only $\Sigma P_{x2}(x = 0)$ matters.

An alternate, but equivalent, approach ¹ to the problem of current-induced torques replaces the spin current by the spin imbalance, defined as the difference $\Delta\mu = \mu_\uparrow - \mu_\downarrow \simeq 10^{-4} \text{ eV}$ between the spin-up and spin-down Fermi levels at a given point of the Fermi surface. As before, only the electrons on the $k_x^N > 0$ half matter, because some of them have their spin along $\vec{S}_1$, and because they enter F_2 .

When $\Delta\mu < 0$, the quantity $\Delta\mu$ ‘‘pumps’’ the electron gas, just like the difference between valence-band and conduction-band Fermi levels does ¹² in a laser diode, resulting in stimulated emission of spin waves, i.e., in precession. The current threshold where precession begins is given ^{1,6} by $\Delta\mu + \hbar\omega = 0$, where ω is the angular frequency of precession, at any temperature. A mathematically identical condition applies ¹² to the threshold of a laser diode.

In the case of Fermi-surface translation, $\Delta\mu$ is proportional to $\delta k_x^+ - \delta k_x^-$ or to j_x :

$$\Delta\mu = -2 \frac{\alpha_1 - 1}{\alpha_1 + 1} \frac{\hbar k_x^N}{e n_e^N} \frac{T_{av}}{2} j_x = \frac{\hbar^2}{m} k_x^N (\delta k_x^+ - \delta k_x^-) \frac{T_{av}}{2}. \quad (7)$$

Here, $\alpha_1 = j_x^\uparrow/j_x^\downarrow$ is the local ratio of spin-up to spin-down current densities in N, and n_e^N the electron density per unit volume in N. We average k_x^N over the $k_x^N > 0$ half of the Fermi surface, obtaining $k_x^N \simeq k_N/2$. Similarly, T_{av} is some average of T over that half. As before, the $T_{av}/2$ factor is present because only transmitted $k_x^N > 0$ waves are active for SWASER action. We combine Eqs. (6,7) and obtain

$$\frac{\Sigma P_{x2}(x=0)}{\Delta\mu} = -\frac{k_N \sin\theta}{8\pi^2} \frac{2}{T_{av}} \int_0^{\pi/2} T \frac{(2k_x^N)^2 (k_x^\uparrow + k_x^\downarrow) \cos\alpha \sin\alpha d\alpha}{(k_x^N + k_x^\uparrow)(k_x^N + k_x^\downarrow)}. \quad (8)$$

We see that ΣP_{x2} and $\Delta\mu$ vary in a constant ratio when j_x or $\alpha_1 = j_x^\uparrow/j_x^\downarrow$ changes. This reflects the fact that the Slonczewski theory, based on ΣP_{x2} , is nearly equivalent to the SWASER theory based on $\Delta\mu$. The only significant difference is that the first theory uses only bulk damping, and the second theory only surface damping.

IV. TOTAL SPIN CURRENT IN CASE OF EXPANDED OR CONTRACTED FERMI SURFACE

There exists a different kind of spin imbalance, associated with isotropic expansion or contraction of the Fermi surface rather than translation (Fig 2b). It is the one originally introduced by Aronov¹³ and by Johnson and Silsbee¹⁴. This quantity, which we denote³ by $\Delta\bar{\mu}$, is an average of $\mu_\uparrow - \mu_\downarrow$ over the whole Fermi surface, not just one half. Since it depends on $j_x^\uparrow$ and $j_x^\downarrow$ values over a range of x of the order of a spin-diffusion length, we call it the nonlocal spin imbalance. It may exist even at locations where the electrical current density is zero. Like $\Delta\mu < 0$, $\Delta\bar{\mu} < 0$ can be used^{3,6} to induce spin precession in a multilayer. For the configuration of Fig. 1a, $\Delta\bar{\mu}$ has the same sign as $\Delta\mu$.

We can calculate³ $\Delta\bar{\mu}$ for the multilayer of Fig. 1a at the $N - F_2$ interface by solving the spin-diffusion equations in one dimension, assuming the F_1 and N_2 thicknesses to be much larger than a local spin-diffusion length l_{sr} , and the N, F_2 thicknesses much smaller than a local l_{sr} . A formula for $\Delta\bar{\mu}$ was given as Eq. (5) of Ref. 3. By comparing the formula to our Eq. (7) for $\Delta\mu$, one obtains roughly

$$\frac{\Delta\mu}{\Delta\bar{\mu}} \leq \left(\frac{\Lambda_\downarrow}{l_{sr}}\right)_{F1} + \left(\frac{\Lambda_\downarrow}{l_{sr}}\right)_{N2}. \quad (9)$$

Here, $\Lambda_\downarrow$ and l_{sr} are the spin-down mean free path and the spin-diffusion length, and F1, N2 refer to layers F_1 and N_2 . We see from Eq. (9) that the $\Delta\bar{\mu}$ mechanism is usually dominant over the $\Delta\mu$ mechanism, since we have $\Lambda_\downarrow/l_{sr} \simeq 0.1 - 0.01$ in most magnetic materials¹⁵. This is helped by the fact that $\Lambda_\downarrow < \Lambda_\uparrow$ in Co, Ni, Ni-Fe.

The spin-current component P_{x2} of one electron is still given by Eq. (5). It is still true that only electrons located between the spin-up and spin-down Fermi surfaces (Fig. 2b) contribute to the total spin current of the electron distribution, which we denote now by $\Sigma\overline{P}_{x2}$ to differentiate it from the translation case. We consider a momentum-space volume element d^2k at an angle α to the k_x^N axis, containing d^2N states of one spin:

$$\begin{aligned} d^2k &= k_N^2 2\pi \sin\alpha d\alpha \delta k_N \\ d^2N &= V_N d^2k / (8\pi^3). \end{aligned} \quad (10)$$

Here, δk_N is the radial distance between Fermi surfaces, now independent of α . It is related to $\Delta\overline{\mu}$ by

$$\Delta\overline{\mu} = \frac{\hbar^2}{m} k_N \delta k_N \frac{T'_{av}}{2}. \quad (11)$$

The quantity T'_{av} is a slightly different average of T than T_{av} . Using Eqs. (10, 11), we integrate the P_{x2} of Eqs. (5) over all number elements d^2N to obtain $\Sigma\overline{P}_{x2}$. As before, only the $k_x^N > 0$ half of the Fermi surface contributes:

$$\frac{\Sigma\overline{P}_{x2}(x=0)}{\Delta\overline{\mu}(x=0)} = -\frac{k_N \sin\theta}{16\pi^2} \frac{2}{T'_{av}} \int_0^{\pi/2} T \frac{(2k_x^N)^2 (k_x^\uparrow + k_x^\downarrow) \sin\alpha d\alpha}{(k_x^N + k_x^\uparrow)(k_x^N + k_x^\downarrow)}. \quad (12)$$

This formula for Fermi-surface expansion or contraction differs from that of Eq. (8) for translation by an extra 1/2 factor in the front, as well as by a missing $\cos\alpha$ in the integral. Therefore, the ratios of spin current to spin imbalance given by the two equations are roughly the same. Just as $\Delta\overline{\mu}$ dominates over $\Delta\mu$, $\Sigma\overline{P}_{x2}$ is dominant over ΣP_{x2} if one-dimensional flow is assumed. This implies a considerable reduction of the threshold current where precession starts.

As before, we have $\Sigma\overline{P}_{x2} \simeq 0$ for $x \gg \pi/(k_\uparrow - k_\downarrow)$. Only $\Sigma\overline{P}_{x2}(x=0)$ matters in Eq. (1).

Most multilayer samples used in recent SWASER experiments^{6–8} have current leads flaring out immediately to much wider effective cross section area than that of the multilayer itself. Thus, current flow is not one-dimensional. Because of the increased volume available for spin relaxation in these leads, $\Delta\overline{\mu}$ and $\Sigma\overline{P}_{x2}$ are considerably reduced below their value in one dimension assumed in the present paper, for given current density in layer F_2 . Also, layer F_1 is too thin, leading to the same result. On the other hand, $\Delta\mu$ and ΣP_{x2} in F_2 are not affected by these factors.

In order to maximize $|\Delta\overline{\mu}|$ and $|\Sigma\overline{P}_{x2}|$ and to verify the predictions of the present paper, the cross-section area of layer N_2 , which plays the role of a lead (Fig. 1a), should remain equal to that of layer F_2 , over distances from layer F_2 at least equal to a local spin-diffusion length l_{sr} . And the F_1 thickness should be at least a local l_{sr} , again with constant cross section area. Like us, Fert and

Lee ¹⁶ find that $\Delta\bar{\mu}$ is not determined by interface scattering in the multilayer itself.

The importance of $\Delta\bar{\mu}$ and $\Sigma\bar{P}_{x2}$ can be compared to that of $\Delta\mu$ and ΣP_{x2} by measuring the threshold current of such one-dimensional sample, and comparing to that of a traditional sample with more multidimensional flow. Another way would be to realize the so-called zero-current SWASER ³, which is based on $\Delta\bar{\mu}$ and $\Sigma\bar{P}_{x2}$ alone.

V. EQUIVALENT ELECTRICAL CIRCUIT

Electrical conduction in the multilayer of Fig. 1a can be described by an equivalent dc electrical circuit (Fig. 3). It may be used to calculate $\Delta\bar{\mu}$.

The upper horizontal resistors represent conduction in the spin-down band in F_1 and N_2 , including both interface and bulk scattering, and the lower horizontal resistors conduction in the spin-up band. The vertical resistors represent electron-spin relaxation between the two bands. The dc electrical motor represents the interaction between electrons and spin waves in F_2 . The dc current through the motor corresponds to the rate of electron spin flip in F_2 associated ¹ with spin-wave generation, i.e., with inducing spin precession. And $\Delta\bar{\mu}/e$ at the $N - F_2$ interface is represented by the dc voltage between points D and U. The counter-electromotive force of the motor is equal to $\hbar\omega/e$, and its internal resistance, shown as R_M , is inversely proportional to the number n_m of spin-wave quanta (magnons) in F_2 . This circuit (Fig.3) can be justified on the basis of the spin-diffusion equations ³ and of the formula ¹ for the rate of production of magnons in F_2 .

Consideration of the equivalent circuit, like that of the spin-diffusion equations ³, shows that the SWASER is affected by conduction processes in F_1 and N_2 over a range of x of at least one spin-diffusion length, in one dimension. It also shows that $\Delta\mu$ and ΣP_{x2} could be maximized, for given j_x , in the case of Fermi-surface translation by having a very short spin-relaxation time in layer N_2 as compared to other layers. On the other hand, a long relaxation time in all layers is best in the case of expansion or contraction. This (large) dependence of ΣP_{x2} on spin relaxation in the various layers is absent from Eqs. (31-33) of Waintal et al. ¹⁷, since they ignore spin relaxation and the spin-diffusion equations. Also, they ignore N_2 .

VI. CONCLUSIONS

In the present paper, we demonstrated the existence of a new kind of spin current, connected with contraction and expansion of the Fermi surface. For one-dimensional current flow, it is larger than the traditional spin current based on translation of the Fermi surface. Each spin current is proportional to its own kind of spin imbalance. Finally, we introduced an equivalent dc electrical circuit describing the processes of electrical conduction, spin relaxation and spin-wave emission in a magnetic multilayer traversed by a dc electrical current perpendicular to layers.

I thank Dr Ya. Bazaliy and Dr M. Tsoi for very useful discussions.

REFERENCES

1. L. Berger, Phys. Rev. B 54, 9353 (1996).
2. L. Berger, J. Appl. Phys. 81, 4880 (1997).
3. L. Berger, IEEE Trans. Magn. 34, 3837 (1998).
4. J.C. Slonczewski, J. Magn. Magn. Mater. 159, L1 (1996); J. Magn. Magn. Mater. 195, L261 (1999).
5. Ya.B. Bazaliy, B.A. Jones and S.C. Zhang, Phys. Rev. B 57, R3213 (1998).
6. M. Tsoi, A.G.M. Jansen, J. Bass, W.-C. Chiang, M. Seck, V. Tsoi and P. Wyder, Phys. Rev. Lett. 80, 4281 (1998); 81, 493(E) (1998); M. Tsoi, A.G.M. Jansen, J. Bass, W. C. Chiang, V. Tsoi and P. Wyder, Nature 406, 46 (2000).
7. E.B. Myers, D.C. Ralph, J.A. Katine, R.N. Louie and R.A. Buhrman, Science 285, 867 (1999); J.Z. Sun, J. Magn. Magn. Mater. 202, 157 (1999).
8. J.A. Katine, F.J. Albert, R.A. Buhrman, E.B. Myers and D.C. Ralph, Phys. Rev. Lett. 84, 3149 (2000); F.J. Albert, J.A. Katine, R.A. Buhrman and D.C. Ralph, Appl. Phys. Lett. 77, 3809 (2000).
9. S.M. Rezende, F.M. de Aguiar, M.A. Lucena and A. Azevedo, Phys. Rev. Lett. 84, 4212 (2000).
10. J.Z. Sun, Phys. Rev. B 62, 570 (2000); Ya.B. Bazaliy, B.A. Jones and S.-C. Zhang, preprint cond-mat/0009034.
11. C. Heide, P.E. Zilberman and R.J. Elliott, preprint cond-mat/0005064.
12. M.G.A. Bernard and G. Duraffourg, Phys. Stat. Solidi 1, 699 (1961).
13. A.G. Aronov, JETP Letters, 24, 32 (1976).
14. M. Johnson and R.H. Silsbee, Phys. Rev. Lett. 55, 1790 (1985).
15. T. Valet and A. Fert, Phys. Rev. B, 48, 7099 (1993); A. Fert, J.L. Duvail and T. Valet, Phys. Rev. B 52, 6513 (1995).
16. A. Fert and S.-F. Lee, Phys. Rev. B, 53, 6554 (1996).
17. X. Waintal, E.B. Myers, P.W. Brouwer and D.C. Ralph, Phys. Rev. B, 62, 12317 (2000).

FIGURE CAPTIONS

FIG. 1. a) Multilayer used for current-driven experiments. Thick magnetic layer F_1 with fixed magnetization prepares the spin of conduction electrons in a specific direction. On the other side of thin non-magnetic spacer N are the thin precessing magnetic layer F_2 and the thick non-magnetic layer N_2 . b) Definition of spin coordinates x_2, y_2, z_2 in relation to the fixed atomic spin $\vec{S}_1$ in F_1 and to the precessing atomic spin $\vec{S}_2$ in F_2 .

FIG. 2. a) The circles represent the spin-up and spin-down Fermi surfaces in N. A local electrical current density $j_x > 0$ causes translations by amounts $\delta k_x^+ < 0, \delta k_x^- < 0$ of these Fermi surfaces along k_x , with $\Delta\mu < 0$. b) Now, one Fermi surface is expanded and the other contracted. The radial distance δk_N of the Fermi surfaces is proportional to the nonlocal spin imbalance $\Delta\bar{\mu} < 0$, according to Eq. (11).

FIG. 3. Equivalent dc electrical circuit for conduction processes in the multilayer of Fig. 1a. The upper horizontal resistors represent conduction in the spin-down band in the various layers, and the lower horizontal resistors in the spin-up band. The vertical resistors represent electron-spin relaxation between

the two bands. The dc electrical motor represents the interaction between electrons and spin waves in F_2 .





FIG. 1





FIG. 2




FIG. 3